SolidWorks Automation Suite - Installation Guide

Pre-Installation Checklist

Before installing, ensure you have:

- [] Windows 10/11 (64-bit) operating system
- [] Administrator privileges on the computer
- [] .NET Framework 4.8 or higher installed
- [] SolidWorks 2020 or higher installed and activated
- [] 500 MB free disk space (minimum)
- [] 8 GB RAM (16 GB recommended)
- [] Antivirus temporarily disabled (if causing conflicts)

Installation Steps

Step 1: Download the Installer

- 1. Download SolidWorksAutomation.msi from:
 - Internal network share: \\server\Software\SolidWorksAutomation\
 - Or download from provided link
- 2. Verify file integrity (optional but recommended):

powershell

Get-FileHash SolidWorksAutomation.msi -Algorithm SHA256

Compare with provided hash value.

Step 2: Run the Installer

- 1. **Right-click** SolidWorksAutomation.msi
- 2. Select "Run as administrator"
- 3. If prompted by User Account Control, click "Yes"

Step 3: Welcome Screen

- 1. Read the welcome message
- 2. Click "Next" to continue

Step 4: License Agreement

- 1. Read the End User License Agreement
- 2. Select "I accept the terms in the License Agreement"
- 3. Click "Next"

Step 5: Choose Install Location

Default Location: C:\Program Files\SolidWorksAutomation

To change:

- 1. Click "Change"
- 2. Browse to desired location
- 3. Click "OK"
- 4. Click "Next"

Recommended: Use default location for proper functionality.

Step 6: Select Features

Choose components to install:

✓ Main Application (Required)

- Core application files
- Dependencies
- Configuration files

✓ Documentation (Recommended)

- User guide
- API documentation
- Troubleshooting guide

☐ Sample Workflows (Optional)

- Pre-built workflow examples
- Template workflows

Select features and click "Next"

Step 7: Shortcuts

Choose shortcut locations:

- [x] Create Start Menu shortcut
- [] Create Desktop shortcut

Click "Next"

Step 8: Ready to Install

- 1. Review installation summary
- 2. Click "Install" to begin
- 3. Wait for installation to complete (2-5 minutes)

Step 9: Completion

- 1. Installation complete message appears
- 2. [] Launch SolidWorks Automation Suite
- 3. Click "Finish"

Post-Installation Configuration

First Launch Setup

When you first launch the application:

1. Initial Connection

The application will attempt to connect to SolidWorks:

If SolidWorks is Running:

- Application attaches to running instance
- Connection status shows "Connected"

If SolidWorks is Not Running:

- Application prompts to start SolidWorks
- Click "Yes" to start
- Wait for connection (15-30 seconds)

2. Configure Paths

- 1. Open Settings (Tools → Settings)
- 2. Navigate to "Paths" tab
- 3. Configure folders:

Templates Path: Location of SolidWorks templates

Recommended: C:\SolidWorks\Templates

Workflows Path: Where workflows are saved

Default: %AppData%\SolidWorksAutomation\Workflows

Output Path: Generated files location

Recommended: D:\SolidWorksOutput (or project-specific folder)

Logs Path: Application logs

Default: %AppData%\SolidWorksAutomation\Logs

1. Click "Apply" then "OK"

3. Test Connection

- 1. Click "Connect to SolidWorks" button
- 2. Verify connection status shows "Connected"
- 3. Check SolidWorks version is displayed

Verification

Verify Installation

1. Check Installation Folder:

C:\Program Files\SolidWorksAutomation\

Should contain:

- UnifiedUI.exe
- Configuration files
- Documentation folder
- Templates folder (if selected)

2. Check Start Menu:

- Windows Start
- Search "SolidWorks Automation"
- Shortcut should appear

3. Check Registry:

Open Registry Editor (regedit) and verify:

HKEY CURRENT USER\Software\SolidWorksAutomation

4. Launch Application:

- Click Start Menu shortcut
- Application should launch without errors
- Main window appears within 5 seconds

Test Basic Functionality

1. Connection Test:

- Launch SolidWorks
- Launch SolidWorks Automation
- Verify connection indicator is green

2. Document Test:

- Open a simple part in SolidWorks
- In application, check that active document is detected

3. Settings Test:

- Open Settings (Ctrl+,)
- Verify all tabs are accessible
- Try changing a setting and saving

Network Installation

For deploying to multiple computers:

Option 1: Group Policy Deployment

1. Copy MSI to network share:

\\server\Software\SolidWorksAutomation\SolidWorksAutomation.msi

2. Create GPO:

- Open Group Policy Management
- Create new GPO
- Edit → Computer Configuration → Software Settings → Software Installation
- Right-click → New → Package
- Browse to MSI file
- Select "Assigned"

3. Deploy:

- Link GPO to target OU
- Force update: gpupdate /force
- Installation occurs on next computer restart

Option 2: Silent Installation

For automated deployment:

msiexec /i SolidWorksAutomation.msi /quiet /norestart /log install.log

With Parameters:

msiexec /i SolidWorksAutomation.msi /quiet /norestart ^
 INSTALLFOLDER="C:\CustomPath\SolidWorksAutomation" ^
 ADDLOCAL=MainApplication,Documentation ^
 /log install.log

Parameters:

- /quiet : No user interface

- /norestart : Don't restart computer

- /log : Create log file

- INSTALLFOLDER: Custom install location

- ADDLOCAL : Features to install

Option 3: SCCM Deployment

For System Center Configuration Manager:

1. Create Application:

- SCCM Console → Software Library → Application Management
- Create Application → Manually specify application information

2. Add Deployment Type:

- Type: Windows Installer

- Content: Path to MSI

- Installation program: msiexec /i SolidWorksAutomation.msi /quiet

- Detection method: File system check for UnifiedUI.exe

3. Deploy:

- Distribute content to distribution points
- Deploy to device collection
- Set deployment purpose (Required/Available)

Upgrading

Upgrade from Previous Version

The installer automatically:

- 1. Detects older version
- 2. Removes old version
- 3. Installs new version
- 4. Preserves user data (settings, workflows, logs)

Manual Steps:

1. Backup User Data (optional but recommended):

%AppData%\SolidWorksAutomation\
Copy to safe location

2. Export Settings:

- Open application

- Settings → Export Settings
- Save to file

3. Run New Installer:

- Follow installation steps above
- Installer handles upgrade automatically

4. **Import Settings** (if needed):

- Settings → Import Settings
- Select exported file

5. **Verify**:

- Check version: Help → About
- Test workflows
- Verify connections

Uninstallation

Method 1: Control Panel

- 1. Open Control Panel
- 2. Navigate to **Programs and Features**
- 3. Find "SolidWorks Automation Suite"
- 4. Click "Uninstall"
- 5. Follow prompts
- 6. Click "Yes" to confirm

Method 2: Settings App

- 1. Open Windows Settings (Win+I)
- 2. Go to Apps
- 3. Search for "SolidWorks Automation"
- 4. Click application
- 5. Click "Uninstall"
- 6. Confirm removal

Method 3: Silent Uninstallation

msiexec /x {ProductGUID} /quiet /norestart /log uninstall.log

Or by MSI path:

msiexec /x SolidWorksAutomation.msi /quiet /norestart /log uninstall.log

What Gets Removed

The uninstaller removes:

- Application files
- Start Menu shortcuts

- Desktop shortcuts (if created)
- Registry entries

What Gets Preserved

User data is **NOT** removed:

- Workflows: %AppData%\SolidWorksAutomation\Workflows\
- Settings: %AppData%\SolidWorksAutomation\settings.json
- Profiles: %AppData%\SolidWorksAutomation\Profiles\
- Logs: %AppData%\SolidWorksAutomation\Logs\

Complete Removal

To remove all traces including user data:

- 1. Uninstall application (methods above)
- 2. Delete user data folder:

powershell

Remove-Item -Recurse -Force "\$env:APPDATA\SolidWorksAutomation"

3. Clean registry (optional):

HKEY CURRENT USER\Software\SolidWorksAutomation

Troubleshooting Installation

Issue: "Installation Failed" Error

Cause: Missing prerequisites or permissions

Solution:

- 1. Verify .NET Framework 4.8 is installed
- 2. Run installer as Administrator
- 3. Check disk space (need 500 MB free)
- 4. Disable antivirus temporarily
- 5. Check Windows Event Viewer for details

Issue: ".NET Framework 4.8 Required" Error

Solution:

- 1. Download .NET Framework 4.8 from Microsoft
- 2. Install .NET Framework 4.8
- 3. Restart computer
- 4. Run installer again

Issue: "SolidWorks Not Found" Warning

Solution:

- This is a warning, not an error
- Install SolidWorks 2020 or higher
- Or continue installation (you can install SolidWorks later)

Issue: Installer Hangs or Freezes

Solution:

1. Wait 5-10 minutes (may be processing)

- 2. If still frozen:
- Open Task Manager
- End "msiexec.exe" process
- Restart computer
- Run installer again

Issue: "Another Version Already Installed"

Solution:

- 1. Uninstall existing version first
- 2. Restart computer
- 3. Run new installer

Advanced Configuration

Custom Installation Paths

To install to custom location:

During Installation:

- Step 5: Click "Change"
- Browse to desired location
- Must have write permissions

After Installation (not recommended):

- Move files manually
- Update registry entries
- Update shortcuts

Proxy Configuration

If behind corporate proxy:

1. Configure system proxy:

```
Settings → Network & Internet → Proxy
```

2. Or configure in application:

Settings → Network → Proxy Settings

Firewall Configuration

Allow application through firewall:

- 1. Windows Firewall → Allow an app
- 2. Click "Change settings"
- 3. Click "Allow another app"
- 4. Browse to UnifiedUI.exe
- 5. Check both Private and Public
- 6. Click "Add"

Support

Installation Support

If you encounter issues:

1. Check Installation Log:

%TEMP%\MSI*.log
Sort by date, open most recent

2. Contact Support:

- Email: support@example.com

- Include: Installation log, error messages, system info

3. Community Help:

- GitHub Issues: https://github.com/swiffc/Solidworks-Automation/issues

- Search for similar issues first

Document Version: 1.0.0

Last Updated: October 29, 2025